

XA RISK REWARD RATIO



To draw lines on the chart, click the pencil button, then, anywhere on the chart.



To delete the drawn lines from the chart, click the scissors button.



The viewfinder button maintains the drawn Open line at the current price level. With switched off function you define Open line level yourself by clicking twice on the line and dragging it anywhere on the chart.



Enabling this function causes Loss and Target lines to follow the Open line in parallel during its automatic or manual adjustment.




Switching this function on produces the same results as the function above, plus automatic adjustment of the distance of Loss or Target line, according to riskRewardRatio defined in the settings.


riskRewardRatio

2.0


Position size management




to define independently these lots please mark None option in Calculation tab




position size you can set manually in the Lots




if you want to manage positions size automatically, there are three options to choose from based on the operating balance (EQUITY), by marking Risk Equity in Calculation tab and defining the permissible potential loss as a percentage, as in the example below (for instance, 10%), Lots size will be calculated automatically based on the distance of Loss and Open lines




based on the account balance (BALANCE), by marking Risk Balance in Calculation tab and defining the permissible potential loss as a percentage, as in the example below (for instance, 5%), lots of position size will be calculated automatically based on the distance of Loss and Open lines



the third option consists in defining the amount in the currency of your account and marking Cash Amount in Calculation tab - here, lots of position size is calculated so that the potential loss amounts to the defined sum, and it is also calculated automatically based on the distance of Loss and Open lines



Irrespective of what option you choose, the program will inform you about the percentage of your account that you risk with agiven positions.



you are also able to choose the color in the settings to inform you about your acceptable risk or exceeding it. With Calculation None option you should define tolerable risk earlier, through Risk Balance, then go back to None setting - otherwise, the program will inform you with color about exceeding the tolerable risk, as the default value of the variable is 0.

Opening positions

MARKET BUY

To open BUY market position, Loss line should be located below Open line and the current price should be found between Loss line and Target line.

MARKET SELL

To open SELL market position, Loss line should be located above Open line and the current price should be found between Loss line and Target line.

BUY STOP

To open BUY STOP pending position, Loss line should be located below Open line and the current price should be found below Open line.

BUY LIMIT

To open BUY LIMIT pending position, Loss line should be located below Open line and the current price should be found above Open line.


SELL STOP

To open SELL STOP pending position, Loss line should be located above Open line and the current price should be found above Open line.


SELL LIMIT

To open SELL LIMIT pending position, Loss line should be located above Open line and the current price should be found below Open line.

If you are unable to open the assignment, you will see NONE



Closing positions



Closing positions is available in Close and Delete tab




Profit button shows current profit from market position, just you need to click Profit button.



Loss button shows current loss from market position, just you need to click Loss button.



All orders button closes all pending orders



Only limit button closes all BUY LIMIT and SELL LIMIT pending orders.